# BPSK system

## 1 Introduction

This document describes the simulation BPSK system in back-to-back configuration.

## 2 Functional Description

A simplified diagram of the system being simulated is presented in the Figure 10. The system simulated takes a random binary string and encodes it in an optical bandpass signal, signal that afterwards is decoded in order to re-obtain the original binary string.

The decoding of the optical signal is accomplished by an homodyne receiver, which combines the signal with a local oscillator with a user-determined phase. The homodyne receiver block output is then fed into a block that compares it with the original binary string and computes the Bit Error Rate (BER) along with it's upper and lower bounds for a certain user defined confidence level.



Figure 1: Overview of the BPSK system being simulated.

System Blocks	netxpto Blocks
BPSK Transmitter	MQamTransmitter
BPSK Receiver	HomodyneReceiver
BER Estimator	BitErrorRate

# 3 System Input Parameters

This system takes into account the following input parameters:

System Parameters	netxpto Parameters
Length of Binary String	NumberOfBits
Number of Samples per Bit	SamplesPerSymbol
Binary String Pattern Length	$\operatorname{pLength}$
Constellation	iqAmplitudesValues
Signal Optical Power	$outOpticalPower\_dBm$
Local Oscillator Optical Power	$LOoutOpticalPower\_dBm$
Local Oscillator Phase	LocalOscillatorPhase
Beam Splitter Transfer Matrix	TransferMatrix
Photodiode Responsivity	Responsivity
Amplification Factor	Amplification
Amplitude of Thermal Noise	NoiseAmplitude
Number of Samples to be discarded	Delay

## 4 Inputs

This system takes no inputs.

## 5 Outputs

This system outputs the following objects:

- Signals:
  - Initial Binary String;
  - Optical Signal with coded Binary String;
  - Decoded Binary String;
- Other:
  - Bit Error Rate report in the form of a .txt file.

#### 6 Simulation Results

We consider the following scenarios:

 $\bullet$  6.1 Basic BPSK back to back with normally distributed thermal noise.

#### 6.1 BPSK with thermal noise

The following results were obtained from the simulation using the following input parameters:

```
NumberOfBits=
                                   1000
       SamplesPerSymbol =
                                   16
                    pLength=
      iqAmplitudesValues=
                                   \{ \{ 1, 0 \}, \{ -1, 0 \} \}
   outOpticalPower\_dBm =
LOoutOpticalPower\_dBm =
                                  -10
     Local Oscillator Phase =
                                   \{ \{ 1/\operatorname{sqrt}(2), 1/\operatorname{sqrt}(2), 1/\operatorname{sqrt}(2), -1/\operatorname{sqrt}(2) \} \}
            TransferMatrix=
              Responsivity=
              Amplification=
                                  1e6
                                   15.397586549153788
           NoiseAmplitude=
                       Delay=
```

The system took the binary string presented in Figure 2 and encoded it into the optical signal in Figure 3. Notice the BPSK constelation of the signal, presented in Figure 4.




Figure 2: Sent binary key.




Figure 3: Sent signal.




Figure 4: Constellation of the sent signal.

Homodyne detection is then performed, using to that effect the local oscillator signal presented in Figure 5. Figures 6 and 7 show the addition of noise to the signal.




Figure 5: Homodyne receiver internal signal: local oscillator used for Homodyne detection.




Figure 6: Homodyne receiver internal signal: subtraction of the signals outputted by the photodiodes.




Figure 7: Homodyne receiver internal signal: amplification of the signal in Figure 6 with added noise.

The result of the homodyne detection is the binary string presented in 8, which is then compared to the original binary string by the BER block, which outputs the report presented in Figure 9.




Figure 8: Decoded binary string, output of the Homodyne receiver block.




Figure 9: Bit-Error-Rate report.

## 7 Block Description

## 7.1 MQAM Transmitter

## 7.2 Homodyne Receiver

#### Introduction

This super-block compresses the function of the following blocks:

- Local Oscillator;
- Balanced Beamsplitter;
- Photodiode;
- Subtractor;
- Amplifier;
- Discretizer;
- Delayer
- Bit Decider;

This compression allows for a cleaner code.

## **Input Parameters**

- $\bullet \ \ Local Oscillator Optical Power$
- $\bullet \ LocalOscillatorOpticalPower\_dBm \\$
- $\bullet$  LocalOscillatorPhase
- $\bullet$  TransferMatrix
- Responsivity
- Amplification
- $\bullet \ \ Noise Amplitude$
- SamplingRate
- Delay
- ReferenceValue

### **Functional Description**

The input signal is evaluated and a binary string is generated from this evaluation.

A diagram of the blocks that constitute this super-block, with the corresponding relations is presented in Figure 10.




Figure 10: Homodyne Receiver Block Diagram.

### **Inputs**

Number: 1

Type: Sequence of impulses modulated by the filter (OpticalSignal)

## Outputs

Number: 1

Type: Binary String (Binary)

#### 7.3 Bit Error Rate

#### **Input Parameters**

 $\bullet$  setConfidence

• setMidReportSize

## **Functional Description**

This block accepts two binary strings and outputs a binary string, outputting a 1 if the two input samples are equal to each other and 0 if not. This block also outputs .txt files with a report of the calculated BER as well as the estimated Confidence bounds for a given probability P. The block allows for mid-reports to be generated, the number of bits between reports is customizable, if it is set to 0 then the block will only output the final report.

#### Input Signals

Number: 1

Type: Binary (DiscreteTimeDiscreteAmplitude)

#### **Output Signals**

Number: 1

 $\mathbf{Type} \colon \operatorname{Binary} \ (\operatorname{DiscreteTimeDiscreteAmplitude})$ 

#### 7.4 Local Oscillator

#### **Input Parameters**

• LocalOscillatorPhase

• LocalOscillatorOpticalPower\_dBm

 $\bullet \ \ Local Oscillator Optical Power$ 

## **Functional Description**

This blocks accepts a complex signal (either with XY polarization or a simple Band Pass signal) and outputs a phase constant complex signal with the same length as the input signal. The phase and optical power are defined by the values of *LocalOscillatorPhase* and *LocalOscillatorOpticalPower* respectively.

## Input Signals

Number: 1

Type: Complex signal (ContinuousTimeContiousAmplitude)

## **Output Signals**

Number: 2

Type: Complex signal (Continuous TimeContious Amplitude)

## 7.5 Beam Splitter

## Input Parameters

• setTransferMatrix

## **Functional Description**

This block accepts two complex signals and outputs two complex signals built from a mixture of the two inputs according to a pre-determined and user defined transfer matrix.

## Input Signals

Number: 2

**Type:** Complex signal (ContinuousTimeContiousAmplitude)

## **Output Signals**

Number: 2

Type: Complex signal (ContinuousTimeContiousAmplitude)

#### 7.6 Photodiode

### Input Parameters

• setResponsivity

#### **Functional Description**

This block accepts two complex signals and outputs two real signals built from an evaluation of the power of the input signals.

## Input Signals

Number: 2

Type: Complex signal (Continuous TimeContious Amplitude)

#### **Output Signals**

Number: 2

Type: Real signal (Continuous Time Contious Amplitude)

#### 7.7 Subtractor

#### **Input Parameters**

This block has no input parameters.

#### **Functional Description**

This block accepts two real signals and outputs one real signals built from subtracting the value of the input signals.

## Input Signals

Number: 2

Type: Real signal (ContinuousTimeContiousAmplitude)

## **Output Signals**

Number: 1

Type: Real signal (ContinuousTimeContiousAmplitude)

## 7.8 Amplifier

## Input Parameters

setAmplification

• setNoiseAmplitude

## **Functional Description**

This block accepts one real signal and outputs one real signal built from multiplying the input signals by a predetermined value. This block also adds random gaussian distributed noise with a user defined amplitude. The multiplying factor and noise amplitude are defined by the values of *Amplification* and *NoiseAmplitude* respectively.

#### Input Signals

Number: 1

Type: Real signal (ContinuousTimeContiousAmplitude)

#### **Output Signals**

Number: 1

Type: Real signal (ContinuousTimeContiousAmplitude)

#### 7.9 Discretizer

## Input Parameters

 $\bullet$  setSamplingRate

#### **Functional Description**

This block accepts one real continuous signal and outputs one real discrete signal built from a sampling of the input signals with a predetermined sampling rate. The sampling rate is defined by the value *SamplingRate*.

## Input Signals

Number: 1

Type: Real signal (ContinuousTimeContiousAmplitude)

## **Output Signals**

Number: 1

**Type**: Real signal (DiscreteTimeContiousAmplitude)

#### 7.10 Delayer

## **Input Parameters**

 $\bullet$  setDelay

## Functional Description

This block accepts one real discrete signal and outputs one real discrete signal discarding a predetermined number of samples of the beginning of the input signal. The number of samples discarded rate is defined by the value *Delay*.

## Input Signals

Number: 1

Type: Real signal (DiscreteTimeContiousAmplitude)

## **Output Signals**

Number: 1

Type: Real signal (DiscreteTimeContiousAmplitude)

#### 7.11 Bit Decider

#### Input Parameters

 $\bullet$  setPosReferenceValue

• setNegReferenceValue

#### **Functional Description**

This block accepts one real discrete signal and outputs a binary string, outputting a 1 if the input sample is above the predetermined reference level and 0 if it is below another reference value. The reference values are defined by the values of PosReferenceValue and NegReferenceValue.

#### Input Signals

Number: 1

Type: Real signal (DiscreteTimeContiousAmplitude)

#### **Output Signals**

Number: 1

**Type**: Binary (DiscreteTimeDiscreteAmplitude)

## 7.12 Bit Error Rate

#### Input Parameters

#### • setConfidence

## **Functional Description**

This block accepts two binary strings and outputs a binary string, outputting a 1 if the two input samples are equal to each other and 0 if not. This block also outputs .txt files with a report of the calculated BER as well as the estimated Confidence bounds for a given probability P. The block allows for mid-reports to be generated, the number of bits between reports is customizable, if it is set to 0 then the block will only output the final report.

## Input Signals

Number: 1

Type: Binary (DiscreteTimeDiscreteAmplitude)

## **Output Signals**

Number: 1

Type: Binary (DiscreteTimeDiscreteAmplitude)

## 8 Known Problems

- Homodyne Super-Block not functioning (problem in inputting signal into it)
- MQAM Transmitter PDF needs to be written
- 8 bits being lost of every signal
- If the bit string length is larger than 512, this first 512 bits are lost
- I don't think it is possible to declare nested subfiles, so I can't put the sub blocks into the homodyne receiver super block manual