

IQ Modulator

October 13, 2016

This block takes the two input signals that correspond to the part of the signal in phase and in quadrature and produces a complex signal. In addition it can also produce a binary signal.

It accepts two input signals and it can produce either one or two output signals.

Input Parameters

- outputOpticalPower{1e-3}
(double)
- outputOpticalWavelength{1550e-9}
(double)
- outputOpticalFrequency{speed_of_light/outputOpticalWavelength}
(double)

Methods

```
IqModulator(vector<Signal *> &InputSig, vector<Signal *> &OutputSig) :Block(InputSig, OutputSig){};
```

```
void initialize(void);
```

```
bool runBlock(void);
```

```
void setOutputOpticalPower(double outOpticalPower) { outputOpticalPower = outOpticalPower; }
```

```
void setOutputOpticalPower_dBm(double outOpticalPower_dBm) { outputOpticalPower = 1e-3*pow(10, outOpticalPower_dBm / 10); }
```

```
void setOutputOpticalWavelength(double outOpticalWavelength) { outputOpticalWavelength = outOpticalWavelength; outputOpticalFrequency = SPEED_OF_LIGHT / outOpticalWavelength; }
```

```
void setOutputOpticalFrequency(double outOpticalFrequency) { outputOpticalFrequency = outOpticalFrequency; outputOpticalWavelength = SPEED_OF_LIGHT / outOpticalFrequency; }
```

Functional Description

The complex signal is multiplied by $\frac{1}{2}\sqrt{\text{outputOpticalPower}}$ in order to reintroduce the information about the energy (or power) of the signal. This signal corresponds to an optical signal and it can be a scalar or have two polarizations along perpendicular axis. It is the signal that is transmitted to the receptor.

The binary signal is sent to the Bit Error Rate (BER) measurement block.

Input Signals

Number: 2

Type: Sequence of impulses modulated by the filter (ContinuousTimeContinuousAmplitude))

Output Signals

Number: 1 or 2

Type: Complex signal (optical) (ContinuousTimeContinuousAmplitude) or binary signal (DiscreteTimeDiscreteAmplitude)

Example

Suggestions for future improvement